

Affected Product Stingray F-504B/C
PCN Title Stingray F-504B/C firmware update 00.03.02.00
PCN No. 2014-03-03 **PCN Issue date** 2014-Apr-09
Contact pcn@alliedvisiontec.com

Type of change

- | | |
|---|--|
| <input type="checkbox"/> Regulatory / Compliance | <input checked="" type="checkbox"/> Firmware Specification |
| <input type="checkbox"/> Mechanical Specification | <input type="checkbox"/> Accessories Specification |
| <input type="checkbox"/> Electrical Specification | <input type="checkbox"/> DISC (Discontinued) |
| <input type="checkbox"/> Optical Specification | <input type="checkbox"/> |

Affected item number(s)

All Stingray 504B/C non fixed version

Reason for change

Bugfix

Change description

Fixed bug behavior (internal number Firewire-62):

The one push operation is interrupted after the first automatically taken image, if the newly computed shutter value

- is below the lower value of auto shutter range or
- is above the upper value of auto shutter range

Last time buy date

n/a

Last time ship date

n/a

Customer action request

n/a

Possible successor

n/a